

Magicard Guide

Language setting for Driver and Printer

Follow the steps below to change the Language setting of the Driver and Printer

DRIVER LANGUAGE

The driver will get the language from the system language on your PC, but you can change it manually:

Depending on your current driver version, Go to: <u>C:\Program Files\Ultra Electronics Ltd\Ultra Installer\Ultra Driver\Support</u> Or

C:\Program Files (x86)\Ultra ID\support

Open Lang.reg in an editor (like Notepad, or Notepad++)

Address 🛅 C:\Program Files\Ultra B	Electronics Ltd\Ultra Installer\Ultra Driver\Sup	port	
	Name 🔺	Size	Туре
File and Folder Tasks	🔰 🔊 icc-increase (20%).reg	1 KB	Registration Entries
🗐 Donomo this file	ang.reg	2 KB	Registration Entries
Rename dris file	TCPMaxTrans.reg	1 KB	Registration Entries
Move this file	all ui.reg	1 KB	Registration Entries
Copy this file	a jui-old.reg	1 KB	Registration Entries
Publish this file to the Web			

Set the last 3 digits to your required language in "dword" at the top: 409 = USA English. "LANGID"=dword:00000409



Then SAVE and close

Now do	uble click	lang.reg:
		. 0 .0

ddress 🛅 C:\Program Files\Ultra Electronics Ltd\Ultra Installer\Ultra Driver\Support				
	Name 🔺	Size	Туре	
File and Folder Tasks 🏾 🖄	Dicc-increase (20%).reg	1 KB	Registration Entries	
Rename this file	ang.reg	2 KB	Registration Entries	
Rename unis nie	TCPMaxTrans.reg	1 KB	Registration Entries	
Move this file	all ui.reg	1 KB	Registration Entries	
Copy this file	alui-old.reg	1 KB	Registration Entries	
Publish this file to the Web				

Choose YES:

Registry	y Editor 🛛 🛛 🕅
2	Are you sure you want to add the information in C:\Program Files\Ultra Electronics Ltd\Ultra Installer\Ultra Driver\Support\Jang.reg to the registry?
	<u>Yes</u> <u>N</u> o
Click	OK:
Registry	y Editor 🛛 🛛 🔀
(į)	Information in C.\Program Files\Ultra Electronics Ltd\Ultra Installer\Ultra Driver\Support\lang.reg has been successfully entered into the registry.
	ОК

Done 😊

PRINTERS LANGUAGE

The **Printer** will get its language from the **Driver**.

It can also be changed using a Quick Command from:

- ID Card Printer <u>Support Utility</u>
- Or from the **Tools tab** in Printer Properties within the latest versions of the driver.

The available languages (for the printer's display) are;

- 0 ENGLISH
- 1 PORTUGUESE
- 2 FRENCH
- 3 GERMAN
- 4 SPANISH 5 - ITALIAN
- 6 POLISH
- 7 ROMANIAN

In the Quick Commands box, type the following;

LNG0 then click Send

Quick Commands		
	LNG0	Send

The will set the printer's language to **English**. Substitute the digit for your preferred language

Please Note:

The next time a print is sent from the driver, the printer will inherit the driver language.

For any further support or questions please contact Magicard Technical Support



support@magicard.com